GDB and x86 assembly

Note: Feel free to come by office hours held by any of the staff. Don't hesitate to ask for help! Our office hours exist to help you. Please visit us if you have any questions or doubts about the material.

A few useful GDB commands

For OS X users: 11db uses different commands. You will be expected to know gdb.

- run (r)
- break (b) \langle func | *addr | line \rangle : add a breakpoint at the specified spot
- step (s): continue to next line, next (n): next line, skip function calls
- stepi (si), nexti (ni): same, but at the instruction level
- continue (c): until next breakpoint
- print (p) $[/f] \langle var |$ \$register \rangle : print the specified value (in format f)
- x/n[b|w][c|x] addr: print n bytes (b) or 4-byte words (w) of memory as char (c) or hex (x). Check GDB reference for other formats. (If displaying bytes, keep in mind that x86 is *little-endian*!)
- info \langle frame | args | locals \rangle : display information about the specified element
- list (l) [line]: show source code around the current line or line
- disassemble (disas) [func]: show the assembly for the current context, or func
- $\langle enter \rangle$: repeat previous command
- layout split: splits the GDB interface into source, assembly, and commands sections.

Intro to x86 assembly

32-bit x86 prefixes its registers with e- (eax, ebp, esp...). x86–64 uses r- (rax, rbp, rsp...).

In AT&T syntax, the suffixes -b, -i, -l, and -q clarify if the instruction operates on bytes, 16-bit words, 32-bit words, or 64-bit words. Source is on the left, destination on the right.

There are 8 general-purpose registers: EAX, EBX, ECX, EDX, ESI, EDI, ESP, and EBP. The registers EBP (base pointer) and ESP (stack pointer) are usually used to delimit the current function's *stack frame*.

The stack grows down (towards lower addresses), by decrementing ESP (subl \$4, %esp) or using the shortcut push: pushl %ebp (decrement ESP by 4 and copy EBP there).

Correspondingly, popl %ebp puts the memory (ESP,ESP+4) into EBP and increments ESP.

The usual *function prologue* is

push %ebp	<pre>// save the top of the previous frame</pre>
mov %esp %ebp	// start new frame by moving EBP down to ESP
sub X %esp	<pre>// X = size of local variables</pre>

And the corresponding exit is

add X %esp	// * (sometimes 'mov %ebp %esp')
pop %ebp	// *
ret	<pre>// pops return address from stack, goes there</pre>
<pre>// * sometimes</pre>	these two lines are replaced with the leave instruction.

Conversely to ret, call *addr* pushes EIP (the instruction pointer, that is, the address of the *next* instruction) onto the stack as a saved return address before jumping to *addr*.

A more thorough overview of 32-bit x86 can be found at https://www.cs.virginia.edu/~evans/cs216/guides/x86.html




Figure 1: Left: memory layout for 32-bit Linux. The stack (left, at top) grows downward. Right: the contents of one frame on the stack.

Security Principles

We discussed the following security principles in lecture (*or in the lecture notes*, which you are responsible for reading):

A. Security is economics	F. Design in security from the start	
B. Least privilege	G. Ensure complete mediation	
C. Know your threat model	-	
D. Defense in depth	H. Division of trust	
E. Consider human factors	I. Consider Shannon's Maxim	

Identify the principle(s) relevant to each of the following scenarios:

- 1. New cars often come with a valet key. This key is intended to be used by valet drivers who park your car for you. The key opens the door and turns on the ignition, but it does not open the trunk or the glove compartment.
- 2. Many home owners leave a house key under the floor mat in front of their door.
- 3. It is not worth it to use a \$400,000 bike lock to protect a \$100 bike.
- 4. Warranties on cell phones do not cover accidental damage, which includes liquid damage. Unfortunately for cell phone companies, many consumers who accidentally damage their phones with liquid will wait for it to dry, then take it in to the store, claiming that "it broke by itself". To combat this threat, many companies have begun to include on the product a small sticker that turns red (and stays red) when it gets wet.
- 5. Social security numbers were not originally designed as a secret identifier. Nowadays, they are often easily obtainable or guessable.
- 6. Even if you use a password on your laptop lockscreen, there is software which lets a skilled attacker with specialized equipment to bypass it.
- 7. Shamir's secret sharing scheme allows us to split a "secret" between multiple people,

so that all of them have to collaborate in order to recover the secret.

- 8. DRM encryption is often effective, until someone can reverse-engineer the decryption algorithm.
- 9. Banks often make you answer your security questions over the phone. Answers to these questions are "low entropy", meaning that they are easy to guess. Some security conscious people instead use a random password as the answer to the security question.¹ However attackers can sometimes convince the phone representative by claiming "I just put in some nonsense for that question".
- 10. Often times at bars, an employee will wait outside the only entrance to the bar, enforcing that people who want to enter the bar form a single-file line. Then, the employee checks each individual's ID to verify if they are 21 before allowing them entry into the bar.

¹Q: "What is your dog's maiden name?". A: "60ba6b1c881c6b87"